



CCS Presentation Systems, Inc.

See us at the CUE Conference!

Tools for Learning Spotlight

Introducing the Mixed Reality Capabilities of the SDC-330 Document Camera

Mixed reality offers an innovative way to foster deeper engagement and understanding by enabling students to interact with 2D, 3D, animated and audio-enriched content. The new SMART Document Camera is now available, and it is mixed reality ready. It works by reading digital markers on physical objects and displaying the enriched content on a SMART Board interactive whiteboard. For example, the document camera reads a digital marker on a flash card and displays a 3D image of an insect, and users can manipulate the image through SMART Notebook collaborative learning software.



CCS will be exhibiting and demonstrating all the latest SMART technology at the upcoming CUE conference in Palm Springs on March 17 - 19. We will be highlighting products shown in these newsletters including the entire SMART line as well as accessories specifically designed to help special needs students, and a variety of other AV technology, too.

Visit [CUE Conference](#) to learn more. See you in the desert!

See mixed reality in action on [YouTube](#).

The new SMART Document Camera will work with SMART's education-specific mixed reality content, which SMART will introduce in summer 2011. This mixed reality content will be fully integrated with SMART Notebook software, so you can incorporate it seamlessly into your lesson activities. As mixed reality content becomes a more integral part of teaching and learning, the SMART Document Camera is ready to support it.



Ask your sales consultant for more information on pricing and availability!

If you don't already receive this newsletter directly, please:

AND now:



February/March Professional Development Calendar

Los Angeles

SMARTBoard Basics -- Feb. 8: 9 a.m. - 12 p.m. and Mar. 14: 9 a.m. - 12 p.m.
 SMARTBoard Beyond the Basics -- Feb. 22: 9 a.m. - 12 p.m. and Mar. 15: 9 a.m. - 12 p.m.
 SMARTBoard Curriculum Integration -- Feb. 22: 1 p.m. - 4 p.m. and Mar. 15: 1 p.m. - 4 p.m.
 SMART Response Basics -- Feb. 8, 2: 1 p.m. - 3 p.m. and Mar. 14: 1 p.m. - 3 p.m.

Orange County

SMARTBoard Basics -- Feb. 16: 9 a.m. - 12 p.m. and Mar. 21: 9 a.m. - 12 p.m.
 SMARTBoard Beyond the Basics -- Feb. 23: 9 a.m. - 12 p.m. and Mar. 22: 9 a.m. - 12 p.m.
 SMARTBoard Curriculum Integrations -- Feb. 23: 1 p.m. - 4 p.m. and Mar. 22: 1 p.m. - 4 p.m.
 SMART Response Basics -- Feb. 16: 1 p.m. - 3 p.m. and Mar. 21: 1 p.m. - 3 p.m.

San Diego

SMARTBoard Basics -- Feb. 8: 9 a.m. - 12 p.m. and Mar. 1: 9 a.m. - 12 p.m.
 SMARTBoard Beyond the Basics -- Feb. 10: 9 a.m. - 12 p.m. and Mar. 3: 9 a.m. - 12 p.m.
 SMARTBoard Curriculum Integration -- Feb. 10: 1 p.m. - 4 p.m. and Mar. 3: 1 p.m. - 4 p.m.
 SMART Response Basics -- Feb. 8: 1 p.m. - 3 p.m. and Mar. 1: 1 p.m. - 3 p.m.
 SMART Slate -- Feb. 9: 10 a.m.-12 p.m.
 SMART Document Camera -- Feb. 9: 3 p.m. - 4:30 p.m.
 Samsung Document Camera -- Feb. 9: 1 p.m. - 2:30 p.m.

San Jose

SMARTBoard Basics -- Feb. 24: 1 p.m. - 4 p.m.
 SMARTBoard Beyond the Basics -- Feb. 25: 1 p.m. - 4 p.m.
 SMARTBoard Curriculum Integration -- Feb. 25: 9 a.m. - 12 p.m.
 SMART Response Basics -- Feb. 24: 9 a.m.-12 p.m.

Tips and Tricks - Troubleshooting Special Edition



Problem: You're unable to annotate smoothly or move objects in SMART Notebook software 10 in Windows 7.

Cause

The Windows 7 Single Finger Panning feature is turned on, and your action is being interpreted as a panning gesture.

Solution

Turn off the Single Finger Panning feature.

To turn off Single Finger Panning

Select Start > Control Panel > Pen and Touch.

The Pen and Touch dialog box appears.

Clear the Turn on Single Finger Panning check box.

Press OK.

MAC OS



Problem: When you touch the interactive screen to select an object, an image of a lined, yellow sheet of paper appears where the pointer should be. If you touch an area outside the image, the image moves to the new location or expands. The image resembles a yellow sticky note or a lined sheet of paper.

Cause

The write-anywhere mode in the Inkwell application program is turned on.

Solution

Turn off the Inkwell application.

To turn off the Inkwell application

Select the Apple menu, and then select System Preferences.

The System Preferences window appears.

Click the Ink icon

The Ink dialog box appears.

If your computer uses Mac OS X operating system software 10.3.9, clear the Allow me to write anywhere option.

OR

If your computer uses Mac OS X operating system software 10.4.x or 10.5.x, clear the Allow me to Ink in any application option.

Restart the computer.

Windows OS

To see a video demonstrations of past Tips and Tricks, go to www.smarterclassrooms.com and log in.

Contact CCS:

Los Angeles - (323) 954-7754 / (888) 454-4489
Orange County - (714) 966-1766 / (888) 788-7225
San Diego - (858) 565-6323 / (888) 293-8428

San Jose - (408) 545-0555 / (888) 657-1778



[Forward email](#)



This email was sent to daveriberi@gmail.com by catrainer@ccsprojects.com | [Update Profile/Email Address](#) | Instant removal with [SafeUnsubscribe™](#) | [Privacy Policy](#).

CCS Presentation Systems, Inc. | 5055 Wilshire Blvd. | Suite 305 | Los Angeles | CA | 90036